



BOSCH

Invented for life

Bosch Video Stitcher 1.6 - Release Notes

Author: Verhaeg Mario (ST-ESS/MKP1)
Date: 07-Nov-2017 16:48

Bosch Video Stitcher 1.6

Introduction

The latest version of the Release Notes is always available on the [Bosch Security Systems Product Catalog](#). Version 1.6.0.63 is the first version of the Bosch Video Stitcher.

New functionality

As this is the first version of the Bosch Video Stitcher no new functionality, compared to earlier versions, has been introduced. An overview of built-in functionality is available in the commercial training.

Installation notes

An installation guide for the Bosch Video Stitcher is available as part of the product download and available in the [Bosch Security Systems product catalogue](#). Bosch strongly recommends following the Bosch Video Stitcher training in order to maximize the quality of the installation.

Hardware drivers

Component	Version
Nvidia Quadro M2000	Quadro Pro Driver for Microsoft Windows 10 (64-Bit) 385.69 (21.September 2017)

Other hardware

The (graphics) hardware mentioned above is used to test the Bosch Video Stitcher and guaranteed to deliver the expected performance. Other, Nvidia based, (graphics) hardware might also work. When other hardware is used limited technical support might be offered, especially related to performance problems.

Resolved issues

As this is the first version of the Bosch Video Stitcher, no previously known issues were resolved in this release.

Known issues

ID	Topic	Description
183566	Configuration	A Bosch Video Stitcher instance may only be added to one BVMS configuration.
184327	Localization	When the language of the operating system is set to Turkish, the Bosch Video Stitcher cannot be licensed. Please set the operating system language to English.
n/a	Performance	In rare instances the Bosch Video Stitcher can be overloaded, which would result in a reduced frame-rate in part of the stitched image.
165614	Virtualization	Due to the extensive usage of hardware acceleration the Bosch Video Stitcher cannot be installed inside a virtual machine.

173467	Configuration	In some situations the preview window might close unexpected.
163306	Regionalization	Augmented reality character rendering is limited to Latin characters.
172386	Configuration	Windows font scaling should not be used, or temporary disabled, when using the Bosch Video Stitcher wizard when configuring the system.
182401	Configuration	If the cameras are, physically, moved after starting the Bosch Video Stitcher wizard, the preview image will not be up-to-date. The wizard needs to be restarted to update the preview image.
180331	Decoders	The stream coming from the Bosch Video Stitcher cannot be displayed on a Bosch Videojet Decoder.